


## How to Install Oracle JInitiator for Windows Vista and Windows 7

In order to access Pelkon 3 System:


- 1) Download and install **Oracle JInitiator 1.3.1.22 (Page 1)**
- 2) Download and install **Java Runtime Environment 6 update 12. (Page 4)**
- 3) Copy **jvm.dll** file. **(Page 10)**

### 1) Download and install Oracle JInitiator 1.3.1.22


a) **Download** Oracle JInitiator 1.3.1.22 from download section.




b) Click **Download Oracle JInitiator 1.3.1.22.**




c) Save the **Jinit.exe** file.



d) Install the **Oracle Jinitiator 1.3.1.22** by clicking **Next** button.




e) Click **O.K** button to finish installation.




2) **Download and install Java Runtime Environment 6 update 12**

a) **Download** Java Runtime Environment from download section.



b) Select **Java SE 6**



c) Select **Java SE Runtime Environment 6u12**

A screenshot of a list of Java SE Runtime Environment versions. The version 'Java SE Runtime Environment 6u12' is highlighted with a red rectangular box. A yellow callout bubble with a pointer to the box contains the text: 'Click 'Java SE Runtime Environment 6u12''.

- [Java SE Runtime Environment 6u20](#)
- [Java SE Runtime Environment 6u19](#)
- [Java SE Runtime Environment 6u18](#)
- [Java SE Runtime Environment 6u17](#)
- [Java SE Runtime Environment 6u16](#)
- [Java SE Runtime Environment 6u15](#)
- [Java SE Runtime Environment 6u14](#)
- [Java SE Runtime Environment 6u13](#)
- [Java SE Runtime Environment 6u12](#)
- [Java SE Runtime Environment 6u11](#)
- [Java SE Runtime Environment 6u10](#)
- [Java SE Runtime Environment 6u7](#)
- [Java SE Runtime Environment for Itanium 6u7](#)

d) Click **Accept License Agreement** to accept agreement.

A screenshot of the license agreement screen for Java SE Runtime Environment 6u12. The text reads: 'You must accept the Oracle Binary Code License Agreement for Java SE to download this software.' Below this, there are two radio buttons: 'Accept License Agreement' (which is selected and highlighted with a red box) and 'Decline License Agreement'. A yellow callout bubble with a pointer to the selected radio button contains the text: 'Tick 'Accept License Agreement''.

Product / File Description	File Size	Download
Java SE Runtime Environment 6u12	18.72 MB	<a href="#">jre-6u12-linux-i586-rpm.bin</a>
Java SE Runtime Environment 6u12	19.23 MB	<a href="#">jre-6u12-linux-i586.bin</a>
Java SE Runtime Environment 6u12	18.72 MB	<a href="#">jre-6u12-linux-ia64-rpm.bin</a>
Java SE Runtime Environment 6u12	19.23 MB	<a href="#">jre-6u12-linux-ia64.bin</a>
Java SE Runtime Environment 6u12	18.20 MB	<a href="#">jre-6u12-linux-x64-rpm.bin</a>
Java SE Runtime Environment 6u12	18.74 MB	<a href="#">jre-6u12-linux-x64.bin</a>
Java SE Runtime Environment 6u12	17.96 MB	<a href="#">jre-6u12-solaris-i586.sh</a>
Java SE Runtime Environment 6u12	23.49 MB	<a href="#">jre-6u12-solaris-sparc.sh</a>
Java SE Runtime Environment 6u12	9.85 MB	<a href="#">jre-6u12-solaris-sparcv9.sh</a>
Java SE Runtime Environment 6u12	6.26 MB	<a href="#">jre-6u12-solaris-x64.sh</a>
Java SE Runtime Environment 6u12	15.52 MB	<a href="#">jre-6u12-windows-ia64.exe</a>
Java SE Runtime Environment 6u12	16.16 MB	<a href="#">jre-6u12-windows-x64-p.exe</a>
Windows Kernel Installation	221.90 KB	<a href="#">jre-6u12-windows-i586-p-iftw-k.exe</a>
Windows Offline Installation	15.52 MB	<a href="#">jre-6u12-windows-i586-p.exe</a>
Windows Online Installation	593.40 KB	<a href="#">jre-6u12-windows-i586-p-iftw.exe</a>

[Back to top](#)

e) Click “jre-6u12-windows-i586-p.exe” for Window Offline Installation.

**Java SE Runtime Environment 6u12**

You must accept the [Oracle Binary Code License Agreement for Java SE](#) to download this software.


Thank you for accepting the Oracle Binary Code License Agreement for Java SE; you may now download this software.

Product / File Description	File Size	Download
Java SE Runtime Environment 6u12	18.72 MB	<a href="#">jre-6u12-linux-i586-rpm.bin</a>
Java SE Runtime Environment 6u12	19.23 MB	<a href="#">jre-6u12-linux-i586.bin</a>
Java SE Runtime Environment 6u12	18.72 MB	<a href="#">jre-6u12-linux-ia64-rpm.bin</a>
Java SE Runtime Environment 6u12	19.23 MB	<a href="#">jre-6u12-linux-ia64.bin</a>
Java SE Runtime Environment 6u12	18.20 MB	<a href="#">jre-6u12-linux-x64-rpm.bin</a>
Java SE Runtime Environment 6u12	18.74 MB	<a href="#">jre-6u12-linux-x64.bin</a>
Java SE Runtime Environment 6u12	17.96 MB	<a href="#">jre-6u12-solaris-i586.sh</a>
Java SE Runtime Environment 6u12	23.49 MB	<a href="#">jre-6u12-solaris-sparc.sh</a>
Java SE Runtime Environment 6u12	9.85 MB	<a href="#">jre-6u12-solaris-sparcv9.sh</a>
Java SE Runtime Environment 6u12	6.26 MB	<a href="#">jre-6u12-solaris-x64.sh</a>
Java SE Runtime Environment 6u12	15.52 MB	<a href="#">jre-6u12-windows-ia64.exe</a>
Java SE Runtime Environment 6u12	16.16 MB	<a href="#">jre-6u12-windows-x64-p.exe</a>
Windows Kernel Installation	221.90 KB	<a href="#">jre-6u12-windows-i586-p-ntw-p.exe</a>
Windows Offline Installation	15.52 MB	<a href="#">jre-6u12-windows-i586-p.exe</a>
Windows Online Installation	593.40 KB	<a href="#">jre-6u12-windows-i586-p-ntw.exe</a>

[Back to top](#)

Click 'jre-6u12-windows-i586-p.exe'

- f) Enter the **Username** and **Password** before you start downloading. ( **If you don't have the Oracle account, please click Sign Up link**)



The image shows a screenshot of the Oracle Sign In page. The page is titled "Sign In" and contains a form with two input fields: "Username" and "Password". Below the "Username" field is a link for "[Lost Username?](#)". Below the "Password" field is a link for "[Lost Password?](#)". A red button labeled "Sign In" is positioned below the form. Below the "Sign In" button, there is a section titled "Don't have an Oracle account?" with a link for "[Sign Up](#) for a free Oracle Web account" and a link for "[Need Help?](#)". At the bottom of the page, it says "Powered by Oracle Access Manager 11g". A yellow callout box with a black border and a black shadow points to the "Username" and "Password" input fields. The callout box contains the text "Enter 'User name & Password'".

**Sign In**

Username

[Lost Username?](#)

Password

[Lost Password?](#)

**Sign In**

**Don't have an Oracle account?**  
[Sign Up](#) for a free Oracle Web account  
[Need Help?](#)

Powered by Oracle Access Manager 11g

Enter 'User name & Password'

g) After download is finished, **install the Java Runtime Environment 6u12** by clicking Accept button.





h) Click **Finish** button to finish installation.




3) **Copy jvm.dll file**

a) Copies file **jvm.dll** from **c:/program files/java/jre1.6.0\_12/bin/client**.



b) Paste to **c:/program files/oracle/Jinitiator1.3.1.22/bin/hotspot** to replace existing file.



#### 4) Assessing Pelkon 3 Website

- a) Open Internet Explorer and type **pelkon3.penangport.com.my** at the address bar.



Key in  
Pelkon 3  
address

- b) Click on **Pelkon III Login**.



Click Pelkon  
III Login

c) Key in **Login Id** and **password**.

